

PR225 Project Update for ALP 3.0.382 and Newer

Projects created for PR225 devices in earlier ALP versions may not open correctly in ALP 3.0.382 or newer due to the updated device naming format.


To migrate such projects, we have prepared a dedicated .bat file, which is attached to this email. This file automatically patches the .owle project with the correct device name so that it can be opened in the new ALP version.

Please follow these steps:

1. Create a separate folder.
2. Place the .owle project file created in the earlier ALP version into this folder.
3. Place the attached .bat file into the same folder.
4. Make sure there is only one .owle file in the folder during this operation.
5. Run the **PR225_project_update_ALP3.0.x.bat** file.
6. After the process is completed, try opening the project in ALP 3.0.382 or newer.

If, for any reason, it is not possible to use the **.bat** file, please follow these manual steps:

1. Rename the **.owle** file extension to **.zip**.
2. Extract the archive.
3. Edit the device name in the relevant **.json** file.



```
5926     },
5927     "Discriminator": 1
5928   },
5929   ],
5930   "CommentBlockModels": [],
5931   "DevValue": "PR225_230.2.2",
5932   "WorkRectangle": {
5933     "Location": {
5934       "IsEmpty": false,
5935       "X": 10,
5936       "Y": 0
```

4. Pack the files back into a **.zip** archive.
5. Rename the **.zip** extension back to **.owle**.

After these steps, the project should be compatible with the new ALP version.